



Safely Canning Food at Home



What is home canning?

Home canning, also known as home bottling, is a method of preserving food that prevents spoiling. It uses heat and acid to help preserve food and keep it safe for us to eat. Spoiling can result from exposure to air, microorganisms and moisture losses. Microorganisms or “germs” include bacteria, yeasts and molds. These can produce a sour smell or cause food poisoning. Proper home canning will create a tight seal on the jars to keep air and microorganisms out, and moisture and freshness locked inside.

You can preserve all types of foods. Popular choices include tomatoes, jams, jellies, sauces, fruits, chutneys, relishes, pickles, and vegetables. It is also possible to can meat, fish, poultry, milk and prepared foods like soups and stews. The canning equipment and method that you use will depend on what food you are preserving.

Keeping your food safe

If you are considering the use of home canning to process food for your own consumption or for sale or distribution to consumers, there are a number of things you need to know to ensure that your food products are safe to consume.

Home canning is very safe when done properly. However, improper home canning can increase the risk of botulism. Botulism is a foodborne illness that is caused by the *Clostridium botulinum* bacteria. The bacteria like to grow in environments that are low in acid and oxygen, and high in moisture. The bacteria and toxin that cause botulism are invisible to the naked eye and do not change the colour, odour or taste of food.

When proper home canning techniques are followed, the risk of botulism is very low. The safest home canning choices to start with are high-acid foods like fruits and relishes, pickles and chutneys that need to be made with acid.

Before you start canning

Home canning requires special equipment, such as glass jars, metal lids, metal rings, boiling water canners and pressure canners. If you have never done any canning before, it may be a good idea to take a home canning course, or read current books and magazines on home canning.

Foods for canning are classified into two types: high-acid foods and low-acid foods, and before you start canning, you need to determine the acid level of the food. Each

type of food requires a different method of heat processing to achieve the required temperatures necessary to prevent the growth of harmful bacteria.

High-acid foods (require a boiling water canner)

High-acid foods include those with a pH of less than 4.6, such as fruit, pickles, sauerkraut, jams, jellies, marmalades and fruit butters. A boiling water canner heats food to 100°C (212°F) at sea level. The acid in the food prevents bacteria from growing, while this temperature will kill most yeasts, moulds and bacteria that could be present. As the bacteria that causes botulism does not grow at a pH below 4.6, it is not a concern for high acid foods.

A boiling water canner is sometimes called a “boiling water bath”. It is a large pot with a fitted lid and is usually made of aluminum or porcelain covered steel. It also comes with removable racks for resting the jars.

Low-acid foods (require a pressure canner)

Low-acid foods include those with a pH of more than 4.6, such as meat, seafood, poultry, soup, milk and most fresh vegeta-

bles, except tomatoes. Tomatoes are borderline high-acid food and require an acid, such as lemon juice or vinegar, to be added for safer canning. Mixtures of low and high acid foods, such as spaghetti sauce with meat, vegetables and tomatoes, are considered low-acid foods. For low-acid foods, the required temperatures can only be achieved in a pressure canner to destroy the bacteria which cause botulism.

A pressure canner is a vessel especially designed to treat canned foods. Pressure canners use steam under high pressure to ensure that the low-acid food reaches the high temperatures necessary to eliminate the bacteria that causes botulism. These high temperatures can only be reached with a pressure canner. A pressure canner is not the same as a pressure cooker. A pressure canner usually has a locking lid and comes with a jar rack, a pressure gauge and a steam vent. The pressure gauge must be checked each year to ensure the food is treated at the right pressure. Always follow the instruction manual that came with the pressure canner.

Tips for safe and high-quality canned food

Getting started:

- Start with high-quality foods. Choose freshly picked fruits and vegetables that are not diseased or moldy. Cut any bruised sections out of your produce. Avoid produce that is too ripe.
- Keep your workspace, canning equipment utensils, lids and jars clean during all stages of the canning process.
- Sterilize your jars. This means first washing your jars in hot soapy water and then boiling the jars according to recipe instructions. Washing with just hot water and soap will not sterilize your jars.



- Use the proper jars for home canning or bottling. Only use new self-sealing lids and make sure the sealing compound is not damaged before you use them. While jars without any nicks or cracks can be reused, always use new lids.
 - Listen for a popping sound once your jars have cooled. Check to see if the lid dips down in the middle. This will tell you that the jars have sealed properly.
 - Check the jars after 24 hours to make sure that the lids are still sealed and not leaking. Have a look at them again one week later.
 - Label and date your jars and store in a cool, dark and dry place.
 - Preserve only as much as you will eat in one year.
- Processing your food:**
- Use only current, tested home canning recipes.
 - Use the appropriate canning method, determined by the pH level of your food (i.e. pressure canning for low-acid foods and boiling water baths for high-acid foods).
 - Always read the manufacturer's instructions for your canning equipment and follow recipes carefully. Changing ingredients, jar sizes or cooking times can result in unsafe food.
 - Fill the canning jars while they are still hot. This helps to remove air and creates a tighter seal.
 - Always wipe the mouth of the jar with a clean cloth before placing the lids on.
 - Leave the recommended amount of "headspace" according to the recipe instructions. Headspace is the empty space between the food and the lid. This space is important to creating a tight seal and allows room for the food to expand when it is being heated.

Commercially canned products

The risk of botulism from commercially canned food is low, as manufacturers use strict thermal processes designed to destroy the spores of *C. botulinum*. However, avoid purchasing or using cans that are damaged or bulging, as this could indicate that the contents may not be safe to eat.

Home canned products

As home canned foods are popular gifts year round, make sure that the foods were home canned under strict food safety conditions.

Never eat canned or bottled foods that are dented, leaking or have bulging ends, or if you suspect they have been tampered with. When in doubt, throw it out!

Revised January 2017



Simcoe

P.O. Box 247, 12 Gilbertson Dr.
Simcoe, ON N3Y 4L1
519.426.6170

www.hnhu.org • environmentalhealth@hnhu.org

Caledonia

282 Argyle Street South
Caledonia, ON N3W 1K7
905.318.6623